

## MOZA Aircross 2 Upgrade Tutorial

### Notice

1. There are two methods for updating the firmware on the MOZA Aircross 2. **To upgrade via the [Computer using the MOZA Master Software](#) or [MOZA Master App](#).**
2. For guidance on updating the firmware, follow the video tutorials:  
**Upgrade via mobile phone:** <https://www.youtube.com/watch?v=5n6BZgTUse0>  
**Upgrade via computer:** <https://www.youtube.com/watch?v=BTss9Fbj4zc>

### Download the Software or APP

Download the MOZA Master Software for your computer or smartphone. For the computer once the software is downloaded install the MOZA Master Software.

<https://www.gudsen.com/moza-aircross-2-downloads>

SOFTWARE		
MOZA Master software	 Windows	
MOZA Master software	 Mac OS	
MOZA Master APP	 Android	
MOZA Master for iOS	 App Store	

For more information on the MOZA Master Software follow the link below:

<https://www.gudsen.com/upfile/admin/file/download/MOZA-Master-1.3.0-Tutorial.pdf?v1>

### Aircross 2 with iFocus-M Wireless Motor kit

If you have the Aircross 2 with iFocus-M Wireless Motor kit, please follow steps below to **update the firmware of the iFocus-M**.

<https://www.youtube.com/watch?v=j-J22fwYlig>

<https://www.gudsen.com/upfile/admin/file/download/iFocus-M-upgrade-tutorial.pdf?v1>

## Upgrade via the Computer

1. Turn off the gimbal.




2. Press and hold in the **Aircross 2's center button** (do not release the center button), then **click the power button**. "Boot Mode" will be displayed on the Aircross 2's screen.


3. Connect the gimbal to the computer with a USB Type-C cable.




4. Launch the MOZA Master software on your computer, select and click "AirCross 2" from the device list.



5. The software will automatically identify the device and load the firmware. Press the “Upgrade” button and wait for about 30s.



6. During the upgrade, “Upgrading”, and the progress percentage will be displayed. After the upgrade is completed, the screen will display “Upgrade is over”.



7. Restart the gimbal. To check the firmware version running on the gimbal go to setting-general-about.

## Upgrade via MOZA Master App.

1. Turn off the gimbal.
2. Turn on your smartphone's Bluetooth and Location (Fig1).
3. Press and hold in the **Aircross 2's center button** (do not release the center button), then **click the power button**. "Boot Mode" will be displayed on the Aircross 2's screen.
4. Open the MOZA Master App (Fig2), then press "connect" button to access the device page (Fig 3), then press + button to search for your Aircross 2 device (Fig4).
5. Select Aircross 2 from the device list (Fig5), and then click "connect" to connect your smartphone to the Aircross 2 (Fig6).
6. The App will automatically enter the firmware upgrade mode. Press the "confirm" button (Fig 7&8). The upgrading process can take about 5 minutes for the firmware to be downloaded and installed.
7. The upgrade process will display 100% when the firmware upgrade has completed (Fig9).
8. Disconnect your smartphone from the gimbal and restart the gimbal. Now you are ready to film.




Fig 1.




Fig 2.



Fig 3.




Fig 4.




Fig 5.




Fig 6.




Fig 7.




Fig 8.




Fig 9.